

Strive Scalper Official

SELUP GUIDE

Gol Strive Scalper Built to act. Made to win. D. XAU/USD

All rights reserved by Strive Scalper.





Ù

100

https://t.me/StriveScalperOfficial

Step

- **Open your MT4**
- > Go to file
- > Open data folder
- > MQL4
- > experts
- > copy and paste the strive scalper ex4 file

Step 2

- **Go back to MT4**
- > **Switch on "Auto Trading"** that is near to new order if is green colour mean on, if is red colour mean off.
- > Open XAUUSD / **Gold Chart window**
- > Go-to navigator or (Ctrl + N)
- > Expert Advisor
- > Refresh
- > double click Strive Scalper
- > Enter your license key

Step 3

Go to "**Common Tab**" just above the license settings

- >**Check the box of the "Allow Live Trading", "Allow DLL import" and "Allow import of external experts"**
- > Click Ok

Please contact Strive Scalper customer support to activate your MT4 live account.

Make sure you choose your settings before running Strive Scalper

Detailed Settings

Broker Any low spread broker

Attach to the XAUUSD/GOLD chart. The Chart naming differs according to the broker.

Magic Just some number that does its magic. Always use the same number. Leave it if you don't know what you are doing.

Starting lot size (default 0.01). Lot

Maximum Maximum allowed lot size (default 5.12). Lot

Maximum Maximum trade in 1 cycle. If you **Trades** set this to 3, then it will only trade 0.01, 0.02, 0.04, and wait for profit.

Turn this feature "On" to align with the **Trend** trend and avoid trading against it. **Following** For the risk-takers aiming for higher profits, set it to Off".

Take Profit Set your target profit level in pips. Strive Scalper will close the trade

automatically when it reaches

this point, securing your gains.

1 if you wish to turn off martingale.

Trailing Start trailing after pips. If you want to Start disableTrailing, set this number higher

than Take Profit.

Martingale Use 2.0 for optimal results. Set this to

News Filter Set to "True" to enable News Filter or Mode disable it by setting it to "False".

Note: Please make sure your device time zone follows your location server. (Especially in VPS, VPS device time must follow VPS server location timezone.)

Min. Impact to Filter

Multiplier

Impact Level	News Filtered
Low	All news will be filtered
Medium	Medium and High impact news will be filtered
High	Only High-impact news will be filtered

Stoploss on **Trend Change**

Set "Yes" to allow Stoploss on Trend Change, it allows an immediate stoploss of trades when EA detected a trend change, based on the 'No. of Candles for Stoploss Confirmation' and 'Period used for Stoploss Confirmation' set.

Period used for Stoploss Confirmation

To set what timeframe the Trend Change should be referring to. You can choose from M30, H1 and H4. Default setting is H4.

Example: Stoploss on Trend Change: Yes

No. of Candles for Stoploss Confirmation: 8 Period used for Stoploss Confirmation: H1

after the 8th candlesticks in H1 timeframe, your trades will be stopped loss, and EA will be paused, you need to restart the EA to continue trading.

Your position entered is Sell, trend changed to UPTREND

Start Time (24H)/ End Time (24H)

To set the trading time you wish the EA to trade.

Example:

Start = 4, End = 20, EA will trade from 4am to 8pm following your device/VPS time zone. After 8pm, EA will not place any new trades, until the next day's 4am.

Leverage 1:300 and above

Licence Find the Licence ID from the purchase email.Contact support ID if you are not sure where to find.

Toggle "No" to close the dashboard **Enable** on your chart, by default it is set as "Yes". Dashboard:

Distance Minimum distance before you open between a new trade in pips. The smaller the distance, the faster the martingale **Trades** layer tends to open.

Mode

Trading Mode	Starting Balance	Expected Profit
Super Algo - High Risk	\$5000-10000	15-25%/month
Super Algo - Low Risk	\$3000-10000	15-25%/month
Turbo Scalping	above \$10,000 /> \$10,000	20%~30%/month
M1 Scalping	\$4,000-\$10,000	15%~20%/month
M5 Scalping	\$4,000-\$10,000	10%~20%/month
M15 Swing	\$4,000-\$10,000	10%~15%/month
M30 Swing	low risk \$500-\$1500	5%~15%/month

Reminder: Starting balance might change from time to time, check with our support to get the latest advice

Trailing Step

Do not use any number lower than 5 pips.

Daily **Profit Goal** (%)

The percentage (%) of profit aims to achieve daily, based on the account balance. Once this goal is achieved, the EA will stop trading for the day.

Stop Trading X Minutes Before News:

This setting decides how many minutes before the news you would like to stop trading.

Start Trading X Minutes After News: This setting decides how many minutes after

the news you would like to resume trading.

Stop New Trades

When activated, this feature stops taking new trades after the existing ones are closed with a profit. To resume trading, simply turn it off.

Equity Protection (%)

This feature allows you to safeguard your account balance by setting a percentage (%) threshold.

No. of Candles for Stoploss Confirmation

For you to decide how many candlestick to determine a trend change for Stoploss on Trend Change to refer to. Default setting is 8.

Enable Time restriction?

Set "Yes" to allow time restriction. Set "No" to trade all the time without restriction. During trade restriction, no new trades allowed, including martingale layer, but Take Profit and Stop Loss shall work accordingly.

Trade on Xday

"Yes" to trade on the selected day, "No" to avoid trading on the selected day.